

# System Calls



THE UNIVERSITY OF  
NEW SOUTH WALES

COMP3231 04s1

1


# Contents

- A high-level view of System Calls
  - Mostly from the user's perspective
    - From textbook (section 1.6)
- A look at the R3000
  - A brief overview
  - Mostly focused on exception handling
    - From “Hardware Guide” on class web site
  - Allow me to provide “real” examples of theory
- System Call implementation
  - Case Study: OS/161 system call handling



# Operating System System Calls

Kernel Level



User Level



THE UNIVERSITY OF  
NEW SOUTH WALES

COMP3231 04s1

3

# System Calls

- Can be viewed as special procedure calls
  - Provides for a controlled entry into the kernel
  - While in kernel, they perform a privileged operation
  - Returns to original caller with the result
- The system call interface represents the abstract machine provided by the operating system.



# A Brief Overview of Classes

## System Calls

- From the user's perspective
  - Process Management
  - File I/O
  - Directories management
  - Some other selected Calls
  - There are many more
    - On Linux, see `man syscalls` for a list



# Some System Calls For Process Management

## Process management

Call	Description
pid = fork()	Create a child process identical to the parent
pid = waitpid(pid, &statloc, options)	Wait for a child to terminate
s = execve(name, argv, environp)	Replace a process' core image
exit(status)	Terminate process execution and return status



# Some System Calls For File Management

**File management**

<b>Call</b>	<b>Description</b>
<code>fd = open(file, how, ...)</code>	Open a file for reading, writing or both
<code>s = close(fd)</code>	Close an open file
<code>n = read(fd, buffer, nbytes)</code>	Read data from a file into a buffer
<code>n = write(fd, buffer, nbytes)</code>	Write data from a buffer into a file
<code>position = lseek(fd, offset, whence)</code>	Move the file pointer
<code>s = stat(name, &amp;buf)</code>	Get a file's status information



# Some System Calls For Directory Management

## Directory and file system management

Call	Description
s = mkdir(name, mode)	Create a new directory
s = rmdir(name)	Remove an empty directory
s = link(name1, name2)	Create a new entry, name2, pointing to name1
s = unlink(name)	Remove a directory entry
s = mount(special, name, flag)	Mount a file system
s = umount(special)	Unmount a file system



# Some System Calls For Miscellaneous Tasks

## Miscellaneous

Call	Description
s = chdir(dirname)	Change the working directory
s = chmod(name, mode)	Change a file's protection bits
s = kill(pid, signal)	Send a signal to a process
seconds = time(&seconds)	Get the elapsed time since Jan. 1, 1970



# System Calls

- A stripped down shell:

```
while (TRUE) {  
    type_prompt( );  
    read_command (command, parameters)          /* repeat forever */  
                                                /* display prompt */  
                                                /* input from terminal */  
  
    if (fork() != 0) {  
        /* Parent code */  
        waitpid( -1, &status, 0);                /* fork off child process */  
    } else {  
        /* Child code */  
        execve (command, parameters, 0);         /* wait for child to exit */  
                                                /* execute command */  
    }  
}
```



# System Calls

UNIX	Win32	Description
fork	CreateProcess	Create a new process
waitpid	WaitForSingleObject	Can wait for a process to exit
execve	(none)	CreateProcess = fork + execve
exit	ExitProcess	Terminate execution
open	CreateFile	Create a file or open an existing file
close	CloseHandle	Close a file
read	ReadFile	Read data from a file
write	WriteFile	Write data to a file
lseek	SetFilePointer	Move the file pointer
stat	GetFileAttributesEx	Get various file attributes
mkdir	CreateDirectory	Create a new directory
rmdir	RemoveDirectory	Remove an empty directory
link	(none)	Win32 does not support links
unlink	DeleteFile	Destroy an existing file
mount	(none)	Win32 does not support mount
umount	(none)	Win32 does not support mount
chdir	SetCurrentDirectory	Change the current working directory
chmod	(none)	Win32 does not support security (although NT does)
kill	(none)	Win32 does not support signals
time	GetLocalTime	Get the current time

## Some Win32 API calls



# The MIPS R2000/R3000

- Before looking at system call mechanics in some detail, we need a basic understanding of the MIPS R3000



# MIPS R3000

- RISC architecture – 5 stage pipeline




Figure 1.1. MIPS 5-stage pipeline



# MIPS R3000

- Load/store architecture
  - No instructions that operate on memory except load and store
  - Simple load/stores to/from memory from/to registers
    - Store word: **sw r4, (r5)**
      - Store contents of r4 in memory using address contained in register r5
    - Load word: **lw r3, (r7)**
      - Load contents of memory into r3 using address contained in r7
      - Delay of one instruction after load before data available in destination register
        - » Must always be an instruction between a load from memory and the subsequent use of the register.
    - **lw, sw, lb, sb, lh, sh,....**



# MIPS R3000

- Arithmetic and logical operations are register to register operations
  - E.g., add r3, r2, r1
  - No arithmetic operations on memory
- Example
  - **add r3, r2, r1**  $\Rightarrow r3 = r2 + r1$
- Some other instructions
  - **add, sub, and, or, xor, sll, srl**




# MIPS R3000

- All instructions are encoded in 32-bit
- Some instructions have *immediate* operands
  - Immediate values are constants encoded in the instruction itself
  - Only 16-bit value
  - Examples
    - Add Immediate: **addi r2, r1, 2048**  
 $\Rightarrow r2 = r1 + 2048$
    - Load Immediate : **li r2, 1234**  
 $\Rightarrow r2 = 1234$



# MIPS Registers

- User-mode accessible registers
  - 32 general purpose registers
    - r0 hardwired to zero
    - r31 the *link* register for jump-and-link (JAL) instruction
  - HI/LO
    - 2 \* 32-bits for multiply and divide
  - PC
    - Not directly visible
    - Modified implicitly by jump and branch instructions




# Branching and Jumping

- Branching and jumping have a *branch delay slot*
    - The instruction following a branch or jump is always executed
- |    |                      |
|----|----------------------|
|    | <b>sw \$0, (\$3)</b> |
|    | <b>j 1f</b>          |
|    | <b>li \$2, 1</b>     |
|    | <b>:</b>             |
| 1: | <b>sw \$2, (\$3)</b> |




# Jump and Link

- JAL is used to implement function calls
  - $r31 = PC+8$
- Jump Register (JR) is used to return from function call




# R3000 Address Space Layout

- kuseg:
  - 2 gigabytes
  - TLB translated (mapped)
  - Cacheable
  - user-mode and kernel mode accessible
  - Page size is 4K




# R3000 Address Space Layout

- kseg0:
  - 512 megabytes
  - Fixed translation window to physical memory
    - $0x80000000 - 0x9fffffff$  virtual =  $0x00000000 - 0x1fffffff$  physical
    - TLB not used
  - Cacheable
  - Only kernel-mode accessible
  - Usually where the kernel code is placed




# R3000 Address Space Layout

- kseg1:
  - 512 megabytes
  - Fixed translation window to physical memory
    - $0xa0000000 - 0xbfffffff$  virtual =  $0x00000000 - 0x1fffffff$  physical
    - TLB not used
  - **NOT** cacheable
  - Only kernel-mode accessible
  - Where devices are accessed (and boot ROM)



# R3000 Address Space Layout

- kseg2:
  - 1024 megabytes
  - TLB translated (mapped)
  - Cacheable
  - Only kernel-mode accessible



# System161 Aside

- System/161 simulates an R3000 without a cache.
  - You don't need to worry about cache issues with programming OS161 running on System/161



# Coprocessor 0

- The processor control registers are located in CP0
  - Exception management registers
  - Translation management registers
- CP0 is manipulated using mtc0 (move to) and mfc0 (move from) instructions
  - mtc0/mfc0 are only accessible in kernel mode.



# CP0 Registers

- Exception Management
  - c0\_cause
    - Cause of the recent exception
  - c0\_status
    - Current status of the CPU
  - c0\_epc
    - Address of the instruction that caused the exception
      - » Note the BD bit in c0\_cause
  - c0\_badvaddr
    - Address accessed that caused the exception
- Miscellaneous
  - c0\_prid
    - Processor Identifier
- Memory Management
  - c0\_index
  - c0\_random
  - c0\_entryhi
  - c0\_entrylo
  - c0\_context
- More about these later in course



# c0\_status

31	30	29	28	27	26	25	24	23	22	21	20	19	18	17	16
CU3	CU2	CU1	CU0	0		RE	0		BEV	TS	PE	CM	PZ	SwC	IsC
15						8	7	6	5	4	3	2	1	0	
			IM				0		KUo	IEo	KUp	IEp	KUc	IEc	

Figure 3.2. Fields in status register (SR)

- CU0-3
  - Enable access to coprocessors (1 = enable)
    - CU0 never enabled for user mode
      - Always accessible in kernel-mode regardless of setting
    - CU1 is floating point unit (if present, FPU not in sys161)
    - CU2-3 reserved



# c0\_status

31	30	29	28	27	26	25	24	23	22	21	20	19	18	17	16
CU3	CU2	CU1	CU0	0	RE	0	BEV	TS	PE	CM	PZ	SwC	IsC		
15					8	7	6	5	4	3	2	1	0		
	IM				0	KUo	IEo	KUp	IEp	KUc	IEc				

Figure 3.2. Fields in status register (SR)

- RE
  - Reverse endian
- BEV
  - Boot exception vectors
    - 1 = use ROM exception vectors
    - 0 = use RAM exception vectors
- TS
  - TLB shutdown (1 = duplicate entry, need a hardware reset)



# c0\_status

31	30	29	28	27	26	25	24	23	22	21	20	19	18	17	16
CU3	CU2	CU1	CU0	0		RE	0		BEV	TS	PE	CM	PZ	SwC	IsC
15						8	7	6	5	4	3	2	1	0	
			IM			0		KUo	IEo	KUp	IEp	KUc	IEc		

Figure 3.2. Fields in status register (SR)

- PE
  - Parity error in cache
- CM
  - Cache management
- PZ
  - Cache parity zero
- SwC
  - Access instruction cache as data
- IsC
  - Isolate data cache
- For practical purposes, you can ignore these bits



# c0\_status

31	30	29	28	27	26	25	24	23	22	21	20	19	18	17	16
CU3	CU2	CU1	CU0	0		RE	0		BEV	TS	PE	CM	PZ	SwC	IsC
15							8	7	6	5	4	3	2	1	0
						IM		0	KUo	IEo	KUp	IEp	KUc	IEc	

Figure 3.2. Fields in status register (SR)

- IM
  - Individual interrupt mask bits
  - 6 external
  - 2 software
- KU
  - 0 = kernel
  - 1 = user mode
- IE
  - 0 = all interrupts masked
  - 1 = interrupts enable
    - Mask determined via IM bits
- c, p, o = current, previous, old



# c0\_cause

31	30	29	28	27	16	15	8	7	6	2	1	0
BD	0	CE		0		IP		0	ExcCode		0	

Figure 3.3. Fields in the Cause register

- BD
  - If set, the instruction that caused the exception was in a branch delay slot
- CE
  - Coprocessor error
    - Attempt to access disabled Copro.
- IP
  - Interrupts pending
    - 8 bits indicating current state of interrupt lines
- ExcCode
  - The code number of the exception taken



# Exception Codes

ExcCode Value	Mnemonic	Description
0	Int	Interrupt
1	Mod	"TLB modification"
2	TLBL	"TLB load/TLB store"
3	TLBS	
4	AdEL	Address error (on load/I-fetch or store respectively). Either an attempt to access outside kuseg when in user mode, or an attempt to read a word or half-word at a misaligned address.
5	AdES	

Table 3.2. ExcCode values: different kinds of exceptions



# Exception Codes


<b>ExcCode Value</b>	<b>Mnemonic</b>	<b>Description</b>
6	IBE	Bus error (instruction fetch or data load, respectively). External hardware has signalled an error of some kind; proper exception handling is system-dependent. The R30xx family CPUs can't take a bus error on a store; the write buffer would make such an exception "imprecise".
7	DBE	
8	Syscall	Generated unconditionally by a <i>syscall</i> instruction.
9	Bp	Breakpoint - a <i>break</i> instruction.
10	RI	"reserved instruction"
11	CpU	"Co-Processor unusable"
12	Ov	"arithmetic overflow". Note that "unsigned" versions of instructions (e.g. <i>addu</i> ) never cause this exception.
13-31	-	reserved. Some are already defined for MIPS CPUs such as the R6000 and R4xxx

**Table 3.2. ExcCode values: different kinds of exceptions**



# c0\_epc

- The Exception Program Counter
  - The address of where to restart execution after handling the exception or interrupt
  - BD-bit in c0\_cause is used on rare occasions when one needs to identify the actual exception-causing instruction
  - Example
    - Assume `sw r3, (r4)` causes a page fault exception



# c0\_badvaddr

- The address access that caused the exception
  - Set if exception is
    - MMU related
    - Access to kernel space from user-mode
    - Unaligned memory access
      - 4-byte words must be aligned on a 4-byte boundary



# Exception Vectors

Program address	“segment”	Physical Address	Description
0x8000 0000	kseg0	0x0000 0000	TLB miss on <i>kuseg</i> reference only.
0x8000 0080	kseg0	0x0000 0080	All other exceptions.
0xbfc0 0100	kseg1	0x1fc0 0100	Uncached alternative <i>kuseg</i> TLB miss entry point (used if SR bit BEV set).
0xbfc0 0180	kseg1	0x1fc0 0180	Uncached alternative for all other exceptions, used if SR bit BEV set).
0xbfc0 0000	kseg1	0x1fc0 0000	The “reset exception”.

Table 4.1. Reset and exception entry points (vectors) for R30xx family



# Hardware exception handling

PC

0x12345678

- Let's now walk through an exception
  - Assume an interrupt occurred as the previous instruction completed
  - Note: We are in user mode with interrupts enabled

EPC

?

Cause

?

Status

KUo IEo KUp IEp KUc IEc

?	?	?	?	1	1
---	---	---	---	---	---

Badvaddr

?




THE UNIVERSITY OF  
NEW SOUTH WALES

COMP3231 04s1

37

# Hardware exception handling



# Hardware exception handling

PC

0x12345678

Kernel Mode is set, and previous mode shifted along

Interrupts disabled and previous state shifted along

Status

KUo IEo KUp IEp KUc IEc

?	?	1	1	0	0
---	---	---	---	---	---

Badvaddr

The Badvaddr register is shown as a blue horizontal bar with two question marks at its ends. Two red arrows originate from the right side of the register and curve upwards towards the Status register, indicating that the value of Badvaddr is being shifted along into the Status register.



# Hardware exception handling

PC

0x12345678

EPC

0x12345678

Cause

0

Status

KUo IEo KUp IEp KUc IEc


? ? 1 1 0 0

Code for the  
exception placed in  
Cause. Note  
Interrupt code = 0

Badvaddr

?

# Hardware exception handling



# Hardware exception handling

PC

0x80000080

- CPU is now running in kernel mode at 0x80000080, with interrupts disabled
- All information required to
  - Find out what caused the exception
  - Restart after exception handlingis in coprocessor registers

EPC


0x12345678

Cause



Status

KUo IEo KUp IEp KUc IEc



Badvaddr

?



THE UNIVERSITY OF  
NEW SOUTH WALES

COMP3231 04s1

42

# Returning from an exception

- For now, let's ignore
  - how the exception is actually handled
  - how user-level registers are preserved
- Let's simply look at how we return from the exception



# Returning from an exception

PC

0x80001234

- This code to return is

```
lw    r27, saved_epc
nop
jr    r27
rfe
```

EPC

0x12345678

Cause



Status

KUo IEo KUp IEp KUc IEc

Bad

Load the contents of  
EPC which is usually  
saved somewhere when  
the exception was  
originally taken



THE UNIVERSITY OF  
NEW SOUTH WALES

# Returning from an exception

PC

0x12345678

EPC

0x12345678

- This code to return is

```
lw    r27, saved_epc
nop
jr    r27
rfe
```

Cause

0

Status

KUo IEo KUp IEp KUc IEc

1	1	0	0
---	---	---	---

Store the EPC back in  
the PC



THE UNIVERSITY OF  
NEW SOUTH WALES

COMP3231 04s1

45

# Returning from an exception

PC

0x12345678

- This code to return

In the *branch delay slot*,  
execute a *restore from  
exception* instruction

lw r27, saved\_ep  
nop  
jr r27  
rfe

Status

KUo IEo KUp IEp KUc IEc

? ? ? ? 1 1

Badvaddr

?



THE UNIVERSITY OF  
NEW SOUTH WALES

COMP3231 04s1

46

# Returning from an exception

PC

0x12345678

- We are now back in the same state we were in when the exception happened

EPC

0x12345678

Cause



Status

KUo IEo KUp IEp KUc IEc



Badvaddr

?




THE UNIVERSITY OF  
NEW SOUTH WALES

COMP3231 04s1

47


# Function Stack Frames

- Each function call allocates a new stack frame for local variables, the return address, previous frame pointer etc.
- Example: assume f1() calls f2(), which calls f3().




# Function Stack Frames

- Each function call allocates a new stack frame for local variables, the return address, previous frame pointer etc.
- Example: assume f1() calls f2(), which calls f3().



# Function Stack Frames

- Each function call allocates a new stack frame for local variables, the return address, previous frame pointer etc.
- Example: assume f1() calls f2(), which calls f3().



# Software Register Conventions

- Given 32 registers, which registers are used for
  - Local variables?
  - Argument passing?
  - Function call results?
  - Stack Pointer?




# Software Register Conventions

Reg No	Name	Used for
0	zero	Always returns 0
1	at	(assembler temporary) Reserved for use by assembler
2-3	v0-v1	Value (except FP) returned by subroutine
4-7	a0-a3	(arguments) First four parameters for a subroutine
8-15	t0-t7	(temporaries) subroutines may use without saving
24-25	t8-t9	
16-23	s0-s7	Subroutine “register variables”; a subroutine which will write one of these must save the old value and restore it before it exits, so the <i>calling</i> routine sees their values preserved.
26-27	k0-k1	Reserved for use by interrupt/trap handler - may change under your feet
28	gp	global pointer - some runtime systems maintain this to give easy access to (some) “static” or “extern” variables.
29	sp	stack pointer
30	s8/fp	9th register variable. Subroutines which need one can use this as a “frame pointer”.
31	ra	Return address for subroutine



# Stack Frame

- MIPS calling convention for gcc
  - Args 1-4 have space reserved for them



# Example Code

```
main ()                                int sixargs(int a, int b,
{                                         int c, int d, int e,
    int i;                           int f)
                                         {
i =                               return a + b + c + d
sixargs(1,2,3,4,5,6);                  + e + f;
}
}
```



0040011c <main>:

40011c:	27bdffd8	addiu	sp, sp, -40
400120:	afb0024	sw	ra, 36(sp)
400124:	afbe0020	sw	s8, 32(sp)
400128:	03a0f021	move	s8, sp
40012c:	24020005	li	v0, 5
400130:	afa20010	sw	v0, 16(sp)
400134:	24020006	li	v0, 6
400138:	afa20014	sw	v0, 20(sp)
40013c:	24040001	li	a0, 1
400140:	24050002	li	a1, 2
400144:	24060003	li	a2, 3
400148:	0c10002c	jal	4000b0 <sixargs>
40014c:	24070004	li	a3, 4
400150:	afc20018	sw	v0, 24(s8)
400154:	03c0e821	move	sp, s8
400158:	8fb0024	lw	ra, 36(sp)
40015c:	8fbe0020	lw	s8, 32(sp)
400160:	03e00008	jr	ra
400164:	27bd0028	addiu	sp, sp, 40

...



**004000b0 <sixargs>:**

<b>4000b0:</b>	<b>27bdffff8</b>	<b>addiu</b>	<b>sp , sp , -8</b>
<b>4000b4:</b>	<b>afbe0000</b>	<b>sw</b>	<b>s8 , 0 (sp)</b>
<b>4000b8:</b>	<b>03a0f021</b>	<b>move</b>	<b>s8 , sp</b>
<b>4000bc:</b>	<b>afc40008</b>	<b>sw</b>	<b>a0 , 8 (s8)</b>
<b>4000c0:</b>	<b>afc5000c</b>	<b>sw</b>	<b>a1 , 12 (s8)</b>
<b>4000c4:</b>	<b>afc60010</b>	<b>sw</b>	<b>a2 , 16 (s8)</b>
<b>4000c8:</b>	<b>afc70014</b>	<b>sw</b>	<b>a3 , 20 (s8)</b>
<b>4000cc:</b>	<b>8fc30008</b>	<b>lw</b>	<b>v1 , 8 (s8)</b>
<b>4000d0:</b>	<b>8fc2000c</b>	<b>lw</b>	<b>v0 , 12 (s8)</b>
<b>4000d4:</b>	<b>00000000</b>	<b>nop</b>	
<b>4000d8:</b>	<b>00621021</b>	<b>addu</b>	<b>v0 , v1 , v0</b>
<b>4000dc:</b>	<b>8fc30010</b>	<b>lw</b>	<b>v1 , 16 (s8)</b>
<b>4000e0:</b>	<b>00000000</b>	<b>nop</b>	
<b>4000e4:</b>	<b>00431021</b>	<b>addu</b>	<b>v0 , v0 , v1</b>
<b>4000e8:</b>	<b>8fc30014</b>	<b>lw</b>	<b>v1 , 20 (s8)</b>
<b>4000ec:</b>	<b>00000000</b>	<b>nop</b>	
<b>4000f0:</b>	<b>00431021</b>	<b>addu</b>	<b>v0 , v0 , v1</b>
<b>4000f4:</b>	<b>8fc30018</b>	<b>lw</b>	<b>v1 , 24 (s8)</b>
<b>4000f8:</b>	<b>00000000</b>	<b>nop</b>	



4000fc:	00431021	addu	v0 , v0 , v1
400100:	8fc3001c	lw	v1 , 28 (s8)
400104:	00000000	nop	
400108:	00431021	addu	v0 , v0 , v1
40010c:	03c0e821	move	sp , s8
400110:	8fbe0000	lw	s8 , 0 (sp)
400114:	03e00008	jr	ra
400118:	27bd0008	addiu	sp , sp , 8



# System Calls

Continued



THE UNIVERSITY OF  
NEW SOUTH WALES

COMP3231 04s1

58

# User and Kernel Execution

- Simplistically, execution state consists of
  - Registers, processor mode, PC, SP
- User applications and the kernel have their own execution state.
- System call mechanism safely transfers from user execution to kernel execution and back.



# System Call Mechanism in Principle

- Processor mode
  - Switched from user-mode to kernel-mode
    - Switched back when returning to user mode
- SP
  - User-level SP is saved and a kernel SP is initialised
    - User-level SP restored when returning to user-mode
- PC
  - User-level PC is saved and PC set to kernel entry point
    - User-level PC restored when returning to user-level
  - Kernel entry via the designated entry point must be strictly enforced



# System Call Mechanism in Principle

- Registers
  - Set at user-level to indicate system call type and its arguments
    - A convention between applications and the kernel
  - Some registers are preserved at user-level or kernel-level in order to restart user-level execution
    - Depends on language calling convention etc.
  - Result of system call placed in registers when returning to user-level
    - Another convention




# Why do we need system calls?

- Why not simply jump into the kernel via a function call????
  - Function calls do not
    - Change from user to kernel mode
      - and eventually back again
    - Restrict possible entry points to secure locations



# Steps in Making a System Call



There are 11 steps in making the system call  
read (fd, buffer, nbytes)

# MIPS System Calls

- System calls are invoked via a *syscall* instruction.
  - The *syscall* instruction causes an exception and transfers control to the general exception handler
  - A convention (an agreement between the kernel and applications) is required as to how user-level software indicates
    - Which system call is required
    - Where its arguments are
    - Where the result should go




# OS/161 Systems Calls

- OS/161 uses the following conventions
  - Arguments are passed and returned via the normal C function calling convention
  - Additionally
    - Reg v0 contains the system call number
    - On return, reg a3 contains
      - 0: if success, v0 contains successful result
      - not 0: if failure, v0 has the errno.
        - » v0 stored in errno
        - » -1 returned in v0



# CAUTION

- Seriously low-level code follows
- This code is not for the faint hearted



# User-Level System Call Walk Through

```
int read(int filehandle, void *buffer, size_t size)
```

- Three arguments, one return value
- Code fragment calling the read function

400124:	02602021	move a0,s3
400128:	27a50010	addiu a1,sp,16
40012c:	0c1001a3	jal 40068c <read>
400130:	24060400	li a2,1024
400134:	00408021	move s0,v0
400138:	1a000016	blez s0,400194 <docat+0x94>

- Args are loaded, return value is tested



# The read() syscall function

## part 1

0040068c <read>:

```
40068c: 08100190  j    400640 <__syscall>
400690: 24020005  li    v0,5
```

- Appropriate registers are preserved
  - Arguments (a0-a3), return address (ra), etc.
- The syscall number (5) is loaded into v0
- Jump (not jump and link) to the common syscall routine



# The read() syscall function

## part 2

Generate a syscall exception

00400640 <\_\_syscall>:

400640:	0000000c	syscall
400644:	10e00005	beqz a3,40065c <__syscall+0x1c>
400648:	00000000	nop
40064c:	3c011000	lui at,0x1000
400650:	ac220000	sw v0,0(at)
400654:	2403ffff	li v1,-1
400658:	2402ffff	li v0,-1
40065c:	03e00008	jr ra
400660:	00000000	nop



# The read() syscall function

## part 2

00400640 <\_\_syscall>:

400640:	0000000c	syscall
400644:	10e00005	beqz a3, 40065c <__syscall+0x1c>
400648:	00000000	nop
40064c:	3c011000	lui at, 0x1000
400650:	ac220000	sw v0, 0(at)
400654:	2403ffff	li v1, -1
400658:	2402ffff	li v0, -1
40065c:	03e00008	jr ra
400660:	00000000	nop

Test success, if  
yes, branch to  
return from function



# The read() syscall function part 2

```
00400640 <__syscall>:  
 400640: 0000000c      syscall  
 400644: 10e00005      breqz  a3,40065c  
 400648: 00000000      nop  
 40064c: 3c011000      lui     at,0x1000  
 400650: ac220000      sw      v0,0(at)  
 400654: 2403ffff      li      v1,-1  
 400658: 2402ffff      li      v0,-1  
 40065c: 03e00008      jr      ra  
 400660: 00000000      nop
```

If failure, store  
code in *errno*



# The read() syscall function

## part 2

00400640 <\_\_syscall>:

400640:	0000000c	syscall
400644:	10e00005	beqz a3, 40065c
400648:	00000000	nop
40064c:	3c011000	lui at, 0x1000
400650:	ac220000	sw v0, 0(at)
400654:	2403ffff	li v1, -1
400658:	2402ffff	li v0, -1
40065c:	03e00008	jr ra
400660:	00000000	nop

Set read() result to  
-1



# The read() syscall function part 2

```
00400640 <_syscall>:  
 400640: 0000000c      syscall  
 400644: 10e00005      beqz  a3,40065c  
 400648: 00000000      nop  
 40064c: 3c011000      lui    at,0x1000  
 400650: ac220000      sw     v0,0(at)  
 400654: 2403ffff      li     v1,-1  
 400658: 2402ffff      li     v0,-1  
 40065c: 03e00008      jr    ra  
 400660: 00000000      nop
```

Return to location  
after where read()  
was called



# Summary

- From the caller's perspective, the read() system call behaves like a normal function call
  - It preserves the calling convention of the language
- However, the actual function implements its own convention by agreement with the kernel
  - Our OS/161 example assumes the kernel preserves appropriate registers(s0-s8, sp, gp, ra).
- Most languages have similar *support libraries* that interface with the operating system.



# System Calls - Kernel Side

- Things left to do
  - Change to kernel stack
  - Preserve registers by saving to memory (the stack)
  - Leave saved registers somewhere accessible to
    - Read arguments
    - Store return values
  - Do the “read()”
  - Restore registers
  - Switch back to user stack
  - Return to application




```

exception:
    move k1, sp          /* Save previous stack pointer in k1 */
    mfc0 k0, c0_status   /* Get status register */
    andi k0, k0, CST_USER /* Check the we-were-in-user-mode bit */
    beq k0, $0, 1f /* If clear, from kernel, already have stack */
    nop               /* delay slot */

    /* Coming from user mode */
    la k0, curkstack
    lw sp, 0(k0)
    nop

1:
    mfc0 k0, c0_cause /* Note cause */
    j common_exception
    nop

```



Note k0, k1  
registers available  
for kernel use



**exception:**

```
move k1, sp           /* Save previous stack pointer in k1 */
mfc0 k0, c0_status   /* Get status register */
andi k0, k0, CST_Kup /* Check the we-were-in-user-mode bit */
beq k0, $0, 1f /* If clear, from kernel, already have stack */
nop               /* delay slot */

/* Coming from user mode - load kernel stack into sp */
la k0, curkstack    /* get address of "curkstack" */
lw sp, 0(k0)         /* get its value */
nop               /* delay slot for the load */
```

**1:**

```
mfc0 k0, c0_cause   /* Now, load the exception cause. */
j common_exception   /* Skip to common code */
nop               /* delay slot */
```



common\_exception:

```
/*
 * At this point:
 *     Interrupts are off. (The processor did this for us.)
 *     k0 contains the exception cause value.
 *     k1 contains the old stack pointer.
 *     sp points into the kernel stack.
 *     All other registers are untouched.
 */

/*
 * Allocate stack space for 37 words to hold the trap frame,
 * plus four more words for a minimal argument block.
*/
addi sp, sp, -164
```



```

/* The order here must match mips/include/trapframe.h. */

sw ra, 160(sp)      /* dummy for gdb */
sw s8, 156(sp)      /* save s8 */
sw sp, 152(sp)      /* dummy for gdb */
sw gp, 148(sp)      /* save gp */
sw k1, 144(sp)      /* dummy for gdb */
sw k0, 140(sp)      /* dummy for gdb */

sw k1, 152(sp)      /* real saved sp */
nop                  /* delay slot for store */

mfc0 k1, c0_epc     /* Copr.0 reg 13 == PC for
sw k1, 160(sp)      /* real saved PC */

```

These six stores are a “hack” to avoid confusing GDB  
 You can ignore the details of why and how



```
/* The order here must match mips/include/trapframe.h. */
```

```
sw ra, 160(sp)      /* dummy for gdb */
sw s8, 156(sp)      /* save s8 */
sw sp, 152(sp)      /* dummy for gdb */
sw gp, 148(sp)      /* save gp */
sw k1, 144(sp)      /* dummy for gdb */
sw k0, 140(sp)      /* dummy for gdb */
```

```
sw k1, 152(sp)      /* real saved sp */
nop                  /* delay slot for store */
```

```
mfc0 k1, c0_epc    /* Copr.0 reg 13 == PC for exception */
sw k1, 160(sp)      /* real saved PC */
```

The real work starts here



```
sw t9, 136(sp)
sw t8, 132(sp)
sw s7, 128(sp)
sw s6, 124(sp)
sw s5, 120(sp)
sw s4, 116(sp)
sw s3, 112(sp)
sw s2, 108(sp)
sw s1, 104(sp)
sw s0, 100(sp)
sw t7, 96(sp)
sw t6, 92(sp)
sw t5, 88(sp)
sw t4, 84(sp)
sw t3, 80(sp)
sw t2, 76(sp)
sw t1, 72(sp)
sw t0, 68(sp)
sw a3, 64(sp)
sw a2, 60(sp)
sw a1, 56(sp)
sw a0, 52(sp)
sw v1, 48(sp)
sw v0, 44(sp)
sw AT, 40(sp)
sw ra, 36(sp)
```

Save all the registers  
on the kernel stack



```

/*
 * Save special registers.
*/
mfhi t0
mflo t1
sw t0, 32(sp)
sw t1, 28(sp)

/*
 * Save remaining exception context information.
*/
sw k0, 24(sp)                      /* k0 was loaded with cause earlier */
mfc0 t1, c0_status                 /* Copr.0 reg 11 == status */
sw t1, 20(sp)
mfc0 t2, c0_vaddr                  /* Copr.0 reg 8 == faulting vaddr */
sw t2, 16(sp)

/*
 * Pretend to save $0 for gdb's benefit.
*/
sw $0, 12(sp)


```

We can now use the other registers (t0, t1) that we have preserved on the stack



```
/*
 * Prepare to call mips_trap(struct trapframe *)
 */

addiu a0, sp, 16           /* set argument */
jal mips_trap              /* call it */
nop                         /* delay slot */
```



Create a pointer to the base of the saved registers and state in the first argument register




```

struct trapframe {
    u_int32_t tf_vaddr;           /* vaddr register */
    u_int32_t tf_status;          /* status register */
    u_int32_t tf_cause;           /* cause register */
    u_int32_t tf_lo;
    u_int32_t tf_hi;
    u_int32_t tf_ra; /* Saved register 31 */
    u_int32_t tf_at; /* Saved register 1 (AT) */
    u_int32_t tf_v0; /* Saved register 2 (v0) */
    u_int32_t tf_v1; /* etc. */
    u_int32_t tf_a0;
    u_int32_t tf_a1;
    u_int32_t tf_a2;
    u_int32_t tf_a3;
    u_int32_t tf_t0;
    :
    u_int32_t tf_t7;
    u_int32_t tf_s0;
    :
    u_int32_t tf_s7;
    u_int32_t tf_t8;
    u_int32_t tf_t9;
    u_int32_t tf_k0; /* dummy (see exception.S comment) */
    u_int32_t tf_k1; /* dummy */
    u_int32_t tf_gp;
    u_int32_t tf_sp;
    u_int32_t tf_s8;
    u_int32_t tf_epc;
    /* coprocessor 0 epc register
   */
}

```

By creating a pointer to here of type struct trapframe \*, we can access the user's saved registers as normal variables within 'C'

## Kernel Stack



# Now we arrive in the ‘C’ kernel

```
/*
 * General trap (exception) handling function for mips.
 * This is called by the assembly-language exception handler once
 * the trapframe has been set up.
 */
void
mips_trap(struct trapframe *tf)
{
    u_int32_t code, isutlb, iskern;
    int savespl;

    /* The trap frame is supposed to be 37 registers long. */
    assert(sizeof(struct trapframe)==(37*4));

    /* Save the value of curspl, which belongs to the old context. */
    savespl = curspl;

    /* Right now, interrupts should be off. */
    curspl = SPL_HIGH;
```



# What happens next?

- The kernel deals with whatever caused the exception
  - Syscall
  - Interrupt
  - Page fault
  - It potentially modifies the *trapframe*, etc
    - E.g., Store return code in v0, zero in a3
- ‘`mips_trap`’ eventually returns



```
exception_return:
```

```
/*      16(sp)          no need to restore tf_vaddr */
lw t0, 20(sp)           /* load status register value into t0 */
nop                   /* load delay slot */
mtc0 t0, c0_status     /* store it back to coprocessor 0 */
/*      24(sp)          no need to restore tf_cause */

/* restore special registers */
lw t1, 28(sp)
lw t0, 32(sp)
mtlo t1
mthi t0

/* load the general registers */
lw ra, 36(sp)

lw AT, 40(sp)
lw v0, 44(sp)
lw v1, 48(sp)
lw a0, 52(sp)
lw a1, 56(sp)
lw a2, 60(sp)
lw a3, 64(sp)
```



```
lw t0, 68(sp)
lw t1, 72(sp)
lw t2, 76(sp)
lw t3, 80(sp)
lw t4, 84(sp)
lw t5, 88(sp)
lw t6, 92(sp)
lw t7, 96(sp)
lw s0, 100(sp)
lw s1, 104(sp)
lw s2, 108(sp)
lw s3, 112(sp)
lw s4, 116(sp)
lw s5, 120(sp)
lw s6, 124(sp)
lw s7, 128(sp)
lw t8, 132(sp)
lw t9, 136(sp)

/*      140(sp)          "saved" k0 was dummy garbage anyway */
/*      144(sp)          "saved" k1 was dummy garbage anyway */
```



```

lw gp, 148(sp)          /* restore gp */
/*      152(sp)           stack pointer - below */
lw s8, 156(sp)          /* restore s8 */
lw k0, 160(sp)          /* fetch exception return PC into k0 */

lw sp, 152(sp)          /* fetch saved sp (must be last) */

/* done */
jr k0                   /* jump back */
rfe                    /* in delay slot */

.end common_exception

```

Note again that only  
k0, k1 have been  
trashed

