

# I/O Management

## Chapter 5



# Operating System Design Issues

- **Efficiency**
  - Most I/O devices slow compared to main memory (and the CPU)
    - Use of multiprogramming allows for some processes to be waiting on I/O while another process executes
    - Often I/O still cannot keep up with processor speed
    - Swapping may be used to bring in additional Ready processes
      - More I/O operations
- **Optimise I/O efficiency – especially Disk & Network I/O**




# Operating System Design Issues

- **The quest for generality/uniformity:**
  - Ideally, handle all I/O devices in the same way
    - Both in the OS and in user applications
  - Problem:
    - Diversity of I/O devices
    - Especially, different access methods (random access versus stream based) as well as vastly different data rates.
    - Generality often compromises efficiency!
  - Hide most of the details of device I/O in lower-level routines so that processes and upper levels see devices in general terms such as read, write, open, close.



# I/O Software Layers



## Layers of the I/O Software System



# Interrupt Handlers

- **Interrupt handlers**
  - Can execute at (almost) any time
    - Raise (complex) concurrency issues in the kernel
    - Can propagate to userspace (signals, upcalls), causing similar issues
    - Generally structured so I/O operations block until interrupts notify them of completion
      - `kern/dev/lamebus/lhd.c`



# Interrupt Handler Example

```
static int
lhd_io(struct device *d,
       struct uio *uio)
{
    ...
    /* Loop over all the sectors
     * we were asked to do. */
    for (i=0; i<len; i++) {
        /* Wait until nobody else
         * is using the device. */
        P(lh->lh_clear);
        ...
        /* Tell it what sector we want... */
        lhd_wreg(lh, LHD_REG_SECT, sector+i);
        /* and start the operation. */
        lhd_wreg(lh, LHD_REG_STAT, statval);
        /* Now wait until the interrupt
         * handler tells us we're done. */
        P(lh->lh_done);
        /* Get the result value
         * saved by the interrupt handler. */
        result = lh->lh_result;
    }
}
```

**INT**

**SLEEP**

```
lhd_iodone(struct lhd_softc *lh, int err)
{
    lh->lh_result = err;
    V(lh->lh_done);
}

void
lhd_irq(void *vlh)
{
    ...
    val = lhd_rdreg(lh, LHD_REG_STAT);

    switch (val & LHD_STATEMASK) {
        case LHD_IDLE:
        case LHD_WORKING:
            break;
        case LHD_OK:
        case LHD_INVSECT:
        case LHD_MEDIA:
            lhd_wreg(lh, LHD_REG_STAT, 0);
            lhd_iodone(lh,
                      lhd_code_to_errno(lh, val));
            break;
    }
}
```



# Interrupt Handler Steps

- **Save Registers** not already saved by hardware interrupt mechanism
- (Optionally) **set up context** for interrupt service procedure
  - Typically, handler runs in the context of the currently running process
    - No expensive context switch
- **Set up stack** for interrupt service procedure
  - Handler usually runs on the kernel stack of current process
- **Ack/Mask interrupt controller**, re-enable other interrupts
  - What does this imply?



# Interrupt Handler Steps

- **Run interrupt service procedure**
  - Acknowledges interrupt at device level
  - Figures out what caused the interrupt
    - Received a network packet, disk read finished, UART transmit queue empty
  - If needed, it signals blocked device driver
- **In some cases, will have woken up a higher priority blocked thread**
  - Choose newly woken thread to schedule next.
  - Set up MMU context for process to run next
  - What if we are nested?
- **Load new/original process' registers**
- **Re-enable interrupt; Start running the new process**




# Sleeping in Interrupts

- Interrupt generally has no **context**
  - Unfair to sleep interrupted process
  - Where to get context
    - May be asynchronous (network)
    - Calling context may be on another CPU, dead, etc.
  - What goes into the ready queue?
- What to do?
  - Top and Bottom Half
  - Linux implements with `tasklets` **and** `workqueues`



- Logical position of device drivers is shown here
- Drivers (originally) compiled into the kernel
  - Including OS/161
  - Device installers were technicians
  - Number and types of devices rarely changed
- Nowadays they are dynamically loaded when needed
  - Linux modules
  - Typical users (device installers) can't build kernels
  - Number and types vary greatly
    - Even while OS is running (e.g hot-plug USB devices)

# Device Drivers



# Device Drivers

- **Drivers classified into similar categories**
  - Block devices and character (stream of data) device
- **OS defines a standard (internal) interface to the different classes of devices**
  - Device specs often help, e.g. USB
- **Device drivers job**
  - translate request through the device-independent standard interface (open, close, read, write) into appropriate sequence of commands (register manipulations) for the particular hardware
  - Initialise the hardware at boot time, and shut it down cleanly at shutdown



# Device Driver

- **After issuing the command to the device, the device either**
  - Completes immediately and the driver simply returns to the caller
  - Or, device must process the request and the driver usually blocks waiting for an I/O complete interrupt.
- **Drivers are re-entrant** as they can be called by another process while a process is already blocked in the driver.
  - Re-entrant: Code that can be executed by more than one thread (or CPU) at the same time
    - Manages concurrency using synch primitives




# Device-Independent I/O Software


- There is commonality between drivers of similar classes
- Divide I/O software into device-dependent and device-independent I/O software
- Device independent software includes
  - Buffer or Buffer-cache management
  - Managing access to dedicated devices
  - Error reporting



# Device-Independent I/O Software



(a)



(b)

(a) Without a standard driver interface

(b) With a standard driver interface



# Driver $\Leftrightarrow$ Kernel Interface

- Major Issue is uniform interfaces to devices and kernel
  - Uniform device interface for kernel code
    - Allows different devices to be used the same way
      - No need to rewrite file-system to switch between SCSI, IDE or RAM disk
    - Allows internal changes to device driver with fear of breaking kernel code
  - Uniform kernel interface for device code
    - Drivers use a defined interface to kernel services (e.g. kmalloc, install IRQ handler, etc.)
    - Allows kernel to evolve without breaking existing drivers
  - Together both uniform interfaces avoid a lot of programming implementing new interfaces




# Binary driver interfaces

- Device creators do not wish to reveal driver source code and ship a binary **blob**
  - 3D cards (ATI, NVIDIA)
  - High performance I/O cards (network, disk)
- Kernel ABI (size and position of structures, function locations, etc) must remain constant.
- Problem for open source kernel!



# Device-Independent I/O Software



(a) Unbuffered input

(b) Buffering in user space

(c) *Single buffering* in the kernel followed by copying to user space

(d) Double buffering in the kernel




# No Buffering

- Process must read/write a device a byte/word at a time
  - Each individual system call adds significant overhead
  - Process must wait until each I/O is complete
    - Blocking/interrupt/waking adds to overhead.
    - Many short runs of a process is inefficient (poor CPU cache temporal locality)



# User-level Buffering

- Process specifies a memory *buffer* that incoming data is placed in until it fills
  - Filling can be done by interrupt service routine
  - Only a single system call, and block/wakeup per data buffer
    - Much more efficient



# User-level Buffering

- Issues
  - What happens if buffer is paged out to disk
    - Could lose data while buffer is paged in
    - Could lock buffer in memory (needed for DMA), however many processes doing I/O reduce RAM available for paging. Can cause deadlock as RAM is limited resource
  - Consider write case
    - When is buffer available for re-use?
      - Either process must block until potential slow device drains buffer
      - or deal with asynchronous signals indicating buffer drained



# Single Buffer

- Operating system assigns a buffer in main memory for an I/O request
- Stream-oriented
  - Used a line at a time
  - User input from a terminal is one line at a time with carriage return signaling the end of the line
  - Output to the terminal is one line at a time




# Single Buffer

- Block-oriented
  - Input transfers made to buffer
  - Block moved to user space when needed
  - Another block is moved into the buffer
    - Read ahead



# Single Buffer

- User process can process one block of data while next block is read in
- Swapping can occur since input is taking place in system memory, not user memory
- Operating system keeps track of assignment of system buffers to user processes



(b) Single buffering



# Single Buffer Speed Up

- Assume
  - $T$  is transfer time for a block from device
  - $C$  is computation time to process incoming block
  - $M$  is time to copy kernel buffer to user buffer
- Computation and transfer can be done in parallel
- Speed up with buffering

$$\frac{T + C}{\max(T, C) + M}$$




# Single Buffer

- What happens if kernel buffer is full, the user buffer is swapped out, and more data is received???
  - We start to lose characters or drop network packets



# Double Buffer

- Use two system buffers instead of one
- A process can transfer data to or from one buffer while the operating system empties or fills the other buffer



(c) Double buffering

# Double Buffer Speed Up

- Computation and Memory copy can be done in parallel with transfer
- Speed up with double buffering

$$\frac{T + C}{\max(T, C + M)}$$

- Usually  $M$  is much less than  $T$  giving a favourable result



# Double Buffer

- May be insufficient for really bursty traffic
  - Lots of application writes between long periods of computation
  - Long periods of application computation while receiving data
  - Might want to read-ahead more than a single block for disk



# Circular Buffer

- More than two buffers are used
- Each individual buffer is one unit in a circular buffer
- Used when I/O operation must keep up with process



(d) Circular buffering

# Important Note

- Notice that buffering, double buffering, and circular buffering are all

# Bounded-Buffer Producer-Consumer Problems



# Is Buffering Always Good?


$$\frac{T + C}{\max(T, C) + M} \quad \frac{T + C}{\max(T, C + M)}$$

Single Double

- Can  $M$  be similar or greater than  $C$  or  $T$ ?




# Buffering in Fast Networks



- Networking may involve many copies
- Copying reduces performance
  - Especially if copy costs are similar to or greater than computation or transfer costs
- Super-fast networks put significant effort into achieving zero-copy
- Buffering also increases latency



# I/O Software Summary



Layers of the I/O system and the main functions of each layer

