Bitwise AND

The & operator

- takes two values (1,2,4,8 bytes), treats as sequence of bits
- performs logical AND on each corresponding pair of bits
- result contains same number of bits as inputs

Example:

```
  00100111          AND | 0  1
& 11100011          ----|------
  --------            0 | 0  0
  00100011            1 | 0  1
```

Used for e.g. checking whether a bit is set

Exercise: Checking for odd numbers

One obvious way to check for odd numbers in C

```
int isOdd(int n) {
        return n % 2 == 1;
}
```

Could we use & to achieve the same thing? How? ~

Aside: an alternative to the above

```
int isOdd(int n) {
        return n & 1;
}
```

Bitwise OR

The | operator

- takes two values (1,2,4,8 bytes), treats as sequence of bits
- performs logical OR on each corresponding pair of bits
- result contains same number of bits as inputs

Example:

```
  00100111           OR | 0  1
| 11100011           ----|------
  --------             0 | 0  1
  11100111             1 | 1  1
```

Used for e.g. ensuring that a bit is set

Bitwise NEG

The ~ operator

- takes a single value (1,2,4,8 bytes), treats as sequence of bits
- performs logical negation of each bit
- result contains same number of bits as input

Example:

```
~ 00100111          NEG | 0  1
  --------          ----|------
  11011000              | 1  0
```

Used for e.g. creating useful bit patterns

Bitwise Operations in C

- everything is ultimately a string of bits
- e.g. `unsigned char` = 8-bit value
- e.g. literal bit-string `0b01110001`
- e.g. literal hexadecimal `0x71`
- `&` = bitwise AND
- `|` = bitwise OR
- `~` = bitwise NEG

Bitwise XOR

The `^` operator

- takes two values (1,2,4,8 bytes), treats as sequence of bits
- performs logical XOR on each corresponding pair of bits
- result contains same number of bits as inputs

Example:

```
  00100111      XOR | 0  1
^ 11100011      ----|-----
  --------       0  | 0  1
  11000100       1  | 1  0
```

Used in e.g. generating hashes, graphic operation, cryptography

Left Shift

The << operator

- takes a single value (1,2,4,8 bytes), treats as sequence of bits
- and a small positive integer x
- moves (shifts) each bit x positions to the left
- left-end bit vanishes; right-end bit replaced by zero
- result contains same number of bits as input

Example:

```
00100111 << 2     00100111 << 8
--------          --------
10011100          00000000
```

Right Shift

The >> operator

- takes a single value (1,2,4,8 bytes), treats as sequence of bits
- and a small positive integer x
- moves (shifts) each bit x positions to the right
- right-end bit vanishes; left-end bit replaced by zero**
- result contains same number of bits as input

Example:

```
00100111 >> 2     00100111 >> 8
--------          --------
00001001          00000000
```

Beware: shifts involving negative values are not portable (implementation defined) - use unsigned values to be safe/portable.

Exercise: Bitwise Operations

Given the following variable declarations:

```
// a signed 8-bit value
unsigned char x = 0x55;
unsigned char y = 0xAA;
```

What is the value of each of the following expressions:

- `(x & y)` `(x ^ y)`
- `(x << 1)` `(y << 1)`
- `(x >> 1)` `(y >> 1)`

Exercise: Bit-manipulation

Assuming 8-bit quantities and writing answers as 8-bit bit-strings:
What are the values of the following:

- `25`, `65`, `~0`, `~~1`, `0xFF`, `~0xFF`
- `(01010101 & 10101010)`, `(01010101 | 10101010)`
- `(x & ~x)`, `(x | ~x)`

How can we achieve each of the following:

- ensure that the 3rd bit from the RHS is set to 1
- ensure that the 3rd bit from the RHS is set to 0